The Security function controls access to the application itself and to individual functions within the application.

- The assignment of permissions and user rights is administered and maintained by the client (not Valiant).
- An authorized user can create/edit user logins and passwords for other users.
- Specific permissions can be assigned to an individual user or category of users.
- Vision™ has three (3) user categories: USER, DEFAULT and SUPERUSER.
- All individual Vision™ users must be designated a User or Superuser.

SUPERUSER

- This category is created by Valiant.
- Generally assigned to those individuals who will be assigned the responsibility of the organization, typically the System Administrator.
- Has full security rights and privileges to all Levels, Divisions and application functions.
- Can create security rights and restrictions for all other user categories.
- Users cannot create a Superuser.

DEFAULT

- Special user category designed to create Permission Groups from which individual users may be assigned.
- Default is only used to create the Permission Group individual users cannot be assigned a Default.
- Avoids repetitive steps when creating a group of new users with identical security permissions.

USER


• Individual employees are assigned, either with individually selected Division and Permission rights or by Permission Groups (i.e. Default).

Creating a Superuser

- 1. Select Security from the File Menu
- 2. Enter employee name in Login Name field.
- 3. Select SUPERUSER
- 4. Enter a **Password** (at least 6 characters with 1 capital letter and 1 number)
- 5. Enter **Single Sign-on Acct** (Citrix user ID assigned to employee)
- 6. Check Add/Edit User.
- 7. Enter employee name in Name (Last/First) field.
- 8. Click Save


Note

A Single Sign-on Acct field is available in Vision that allows designated users to automatically log into Vision upon successful completion of the Citrix login at http://www.online.valiant.com.




Creating a DEFAULT Group

- 1. Enter a DEFAULT group name in the **Login Name** field.
- 2. Select **DEFAULT**
- 3. Enter a Password
- Note: A Single Sign-on Acct is not needed for DEFAULT groups.
- Enter the DEFAULT group name in the Name (Last/First) field.
- 6. Click **Save** (<u>before</u> selecting permissions)
- 7. Click **Edit** to continue security setup
- 8. Select applicable permissions.
- 9. Click Save




Creating a USER

- Enter employee name in Login Name field.
- 2. Select USER
- 3. Enter a Password
- Enter Single Sign-on Acct (this is the Citrix user id assigned to the employee)
- 5. Check Add/Edit User, if applicable.
- 6. Enter employee name in Name (Last/First) field.
- 7. Click **Save** (before selecting permissions)
- 8. Click **Edit** to continue security setup
- Click the **Levels** tab and select applicable division, level, or department access.




- 10. Click on the Division tab (Permissions) and select applicable permissions.
- 11. Click Save



Creating a USER (copying a DEFAULT group)

- 1. Complete steps 1-9 above.
- 2. Do <u>NOT</u> select individual permissions.
- 3. Select the DEFAULT group from the **Copy From** drop-down.
- 4. Select "C" (Current Division) to copy to divisions highlighted (under Levels tab) or
- 5. Select "A" (All Divisions) to copy all divisions (under Levels tab)
- 6. Click Save



Note: Please refer to document Vision Security – Permissions with Sample Groups.xls for permission definitions.